
pytest-localstack Documentation

Release 0.1.3

Jaye Doepke

Jul 17, 2018

Contents

1 Features	3
2 Example	5
3 Installation	7
4 TODO	9
5 Table of Contents	11
5.1 Usage	11
5.2 Internals	13
6 Change Log	19
6.1 0.1.3 (2018-07-17)	19
6.2 0.1.2 (2018-06-22)	19
6.3 0.1.1 (2018-04-23)	19
6.4 0.1.0 (2018-03-13)	19
7 Indices and tables	21
Python Module Index	23

pytest-localstack is a plugin for [pytest](#) to create [AWS](#) integration tests via a [Localstack](#) Docker container.

[Read The Docs](#)

Requires:

- [pytest >= 3.3.0](#)
- [Docker](#)

CHAPTER 1

Features

- Create [pytest fixtures](#) that start and stop a Localstack container.
- Temporarily patch botocore to redirect botocore/boto3 API calls to Localstack container.
- Plugin system to easily extend supports to other AWS client libraries such as [aiobotocore](#).

CHAPTER 2

Example

```
import boto3
import pytest_localstack

localstack = pytest_localstack.patch_fixture(
    services=["s3"],      # Limit to the AWS services you need.
    scope='module',        # Use the same Localstack container for all tests in this module.
    autouse=True,          # Automatically use this fixture in tests.
)

def test_s3_bucket_creation():
    s3 = boto3.resource('s3')    # Botocore/boto3 will be patched to use Localstack
    assert len(list(s3.buckets.all())) == 0
    bucket = s3.Bucket('foobar')
    bucket.create()
    assert len(list(s3.buckets.all())) == 1
```


CHAPTER 3

Installation

Install with pipenv:

```
$ pipenv install pytest-localstack
```

(You have `pipenv`, right?)

CHAPTER 4

TODO

- More detailed docs.
- Break Docker container running out of LocalstackSession.
- Make botocore patching more comprehensible.
- Add common test resource fixture factories i.e. S3 buckets, SQS queues, SNS topics, etc.
- Test this works for non-localhost Docker containers.
- Add other client libraries such as [aiobotocore](#).

CHAPTER 5

Table of Contents

5.1 Usage

```
pytest_localstack.patch_fixture(scope='function',      services=None,      autouse=False,
                                 docker_client=None,    region_name='us-east-1',    kinesis_error_probability=0.0, dynamodb_error_probability=0.0,
                                 container_log_level=10,    localstack_verison='latest',
                                 auto_remove=True, pull_image=True, container_name=None,
                                 **kwargs)
```

Create a pytest fixture that temporarially redirects all botocore sessions and clients to a Localstack container.

This is not a fixture! It is a factory to create them.

The fixtures that are created by this function will run a Localstack container and patch botocore to direct traffic there for the duration of the tests.

Since boto3 uses botocore to send requests, boto3 will also be redirected.

Parameters

- **scope** (*str, optional*) – The pytest scope which this fixture will use. Defaults to "function".
- **services** (*list, dict, optional*) – One of
 - A *list* of AWS service names to start in the Localstack container.
 - A *dict* of service names to the port they should run on.Defaults to all services. Setting this can reduce container startup time and therefore test time.
- **autouse** (*bool, optional*) – If `True`, automatically use this fixture in applicable tests. Default: `False`
- **docker_client** (*DockerClient, optional*) – Docker client to run the Localstack container with. Defaults to `docker.client.from_env()`.

- **region_name** (*str, optional*) – Region name to assume. Each Localstack container acts like a single AWS region. Defaults to "us-east-1".
- **kinesis_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into Kinesis API responses.
- **dynamodb_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into DynamoDB API responses.
- **container_log_level** (*int, optional*) – The logging level to use for Localstack container logs. Defaults to logging.DEBUG.
- **localstack_verison** (*str, optional*) – The version of the Localstack image to use. Defaults to "latest".
- **auto_remove** (*bool, optional*) – If `True`, delete the Localstack container when it stops. Default: `True`
- **pull_image** (*bool, optional*) – If `True`, pull the Localstack image before running it. Default: `True`
- **container_name** (*str, optional*) – The name for the Localstack container. Defaults to a randomly generated id.
- ****kwargs** – Additional kwargs will be passed to the `LocalstackSession`.

Returns A pytest fixture.

```
pytest_localstack.session_fixture(scope='function', services=None, autouse=False, docker_client=None, region_name='us-east-1', kinesis_error_probability=0.0, dynamodb_error_probability=0.0, container_log_level=10, localstack_verison='latest', auto_remove=True, pull_image=True, container_name=None, **kwargs)
```

Create a pytest fixture that provides a LocalstackSession.

This is not a fixture! It is a factory to create them.

The fixtures that are created by this function will yield a `LocalstackSession` instance. This is useful for simulating multiple AWS accounts. It does not automatically redirect botocore/boto3 traffic to Localstack (although `LocalstackSession` has a method to do that.) The `LocalstackSession` instance has factories to create botocore/boto3 clients that will connect to Localstack.

Parameters

- **scope** (*str, optional*) – The pytest scope which this fixture will use. Defaults to "function".
- **services** (*list, dict, optional*) – One of:
 - A `list` of AWS service names to start in the Localstack container.
 - A `dict` of service names to the port they should run on.Defaults to all services. Setting this can reduce container startup time and therefore test time.
- **autouse** (*bool, optional*) – If `True`, automatically use this fixture in applicable tests. Default: `False`
- **docker_client** (`DockerClient`, optional) – Docker client to run the Localstack container with. Defaults to `docker.client.from_env()`.

- **region_name** (*str, optional*) – Region name to assume. Each Localstack container acts like a single AWS region. Defaults to "us-east-1".
- **kinesis_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into Kinesis API responses.
- **dynamodb_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into DynamoDB API responses.
- **container_log_level** (*int, optional*) – The logging level to use for Localstack container logs. Defaults to logging.DEBUG.
- **localstack_verison** (*str, optional*) – The version of the Localstack image to use. Defaults to "latest".
- **auto_remove** (*bool, optional*) – If `True`, delete the Localstack container when it stops. Default: `True`.
- **pull_image** (*bool, optional*) – If `True`, pull the Localstack image before running it. Default: `True`.
- **container_name** (*str, optional*) – The name for the Localstack container. Defaults to a randomly generated id.
- ****kwargs** – Additional kwargs will be passed to the `LocalstackSession`.

Returns A pytest fixture.

5.2 Internals

5.2.1 LocalstackSession

```
class pytest_localstack.session.LocalstackSession(docker_client,      services=None,
                                                 region_name='us-east-1',    kine-
                                                 sis_error_probability=0.0,   dy-
                                                 namodb_error_probability=0.0,
                                                 container_log_level=10,    lo-
                                                 calstack_verison='latest',
                                                 auto_remove=True,
                                                 pull_image=True,           con-
                                                 tainer_name=None, use_ssl=False,
                                                 **kwargs)
```

Run a localstack Docker container.

This class can start and stop a Localstack container, as well as capture its logs. It also implements a plugin system to add factories for the various AWS client libraries (botocore, boto3, etc).

Can be used as a context manager:

```
>>> import docker
>>> client = docker.from_env()
>>> with LocalstackSession(client) as session:
...     s3 = session.boto3.resource('s3')
```

Parameters

- **docker_client** – A docker-py Client object that will be used to talk to Docker.
- **services** (*list / dict, optional*) – One of
 - A list of AWS service names to start in the Localstack container.
 - A dict of service names to the port they should run on.Defaults to all services. Setting this can reduce container startup time and therefore test time.
- **region_name** (*str, optional*) – Region name to assume. Each Localstack container acts like a single AWS region. Defaults to ‘us-east-1’.
- **kinesis_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into Kinesis API responses.
- **dynamodb_error_probability** (*float, optional*) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into DynamoDB API responses.
- **container_log_level** (*int, optional*) – The logging level to use for Localstack container logs. Defaults to `logging.DEBUG`.
- **localstack_verison** (*str, optional*) – The version of the Localstack image to use. Defaults to *latest*.
- **auto_remove** (*bool, optional*) – If True, delete the Localstack container when it stops.
- **container_name** (*str, optional*) – The name for the Localstack container. Defaults to a randomly generated id.
- **use_ssl** (*bool, optional*) – If True use SSL to connect to Localstack. Default is False.
- ****kwargs** – Additional kwargs will be stored in a `kwargs` attribute in case test resource factories want to access them.

5.2.2 Plugins/Hooks

Much like `pytest`, itself, `pytest-localstack` uses `pluggy` to implement a plugin system. These plugins can be used to add additional functionality to `pytest-localstack` and to trigger callbacks when the Localstack container is started and stopped.

```
pytest_localstack.hooksspecs.contribute_to_module(pytest_localstack)
    Hook to add additional functionality to the pytest_localstack module.
```

Primarily used to add importable fixture factories at a top level.

```
pytest_localstack.hooksspecs.contribute_to_session(session)
    Hook to add additional functionality to LocalstackSession.
```

Primarily used to add test resource factories to sessions. See `pytest_localstack.contrib.botocore` for an example of that.

```
pytest_localstack.hooksspecs.pytest_localstack_hookimpl = <pluggy.HookimplMarker object>
    This is a test.
```

```
pytest_localstack.hooksspecs.session_started(session)
    Hook fired when LocalstackSession has started.
```

```
pytest_localstack.hooksspecs.session_starting(session)
```

Hook fired when LocalstackSession is starting.

```
pytest_localstack.hooksspecs.session_stopped(session)
```

Hook fired when LocalstackSession has stopped.

```
pytest_localstack.hooksspecs.session_stopping(session)
```

Hook fired when LocalstackSession is stopping.

Plugins manager.

See also:

[hookspecs](#)

```
pytest_localstack.plugin.register_plugin_module(module_path, required=True)
```

Register hooks in a module with the PluginManager by Python path.

Parameters

- **module_path** (*str*) – A Python dotted import path.
- **required** (*bool*, optional) – If False, ignore ImportError. Default: True.

Returns The imported module.

Raises `ImportError` – If *required* is True and the module cannot be imported.

5.2.3 Contrib

botocore

Test resource factory for the botocore library.

```
class pytest_localstack.contrib.botocore.BotocoreTestResourceFactory(localstack_session)
```

Create botocore clients to interact with a `LocalstackSession`.

Parameters `localstack_session` (`LocalstackSession`) – The session that this factory should create test resources for.

```
client(service_name, *args, **kwargs)
```

Create a botocore client that will use Localstack.

Arguments are the same as `botocore.Session.create_client()`.

```
default_session
```

Return a default botocore Localstack Session.

Most applications only need one Session.

```
patch_botocore()
```

Context manager that will patch botocore to use Localstack.

Since boto3 relies on botocore to perform API calls, this method also effectively patches boto3.

```
session(*args, **kwargs)
```

Create a botocore Session that will use Localstack.

Arguments are the same as `botocore.Session`.

```
class pytest_localstack.contrib.botocore.DefaultCredentialProvider(session=None)
```

Provide some default credentials for Localstack clients.

```
load()
    Return credentials.

class pytest_localstack.contrib.botocore.LocalstackEndpointResolver(localstack_session,
    end-
    points)

Resolve AWS service endpoints based on a LocalstackSession.

construct_endpoint(service_name, region_name=None)
    Resolve an endpoint for a service and region combination.

get_available_endpoints(service_name, partition_name='aws', allow_nonRegional=False)
    List the endpoint names of a particular partition.

get_available_partitions()
    List the partitions available to the endpoint resolver.

valid_regions
    Return a list of regions we can resolve endpoints for.

class pytest_localstack.contrib.botocore.Session(localstack_session, *args, **kwargs)
A botocore Session subclass that talks to Localstack.

create_client(*args, **kwargs)
    Create a botocore client.

pytest_localstack.contrib.botocore.contribute_to_module(pytest_localstack)
    Add patch\_fixture\(\) to pytest_localstack.

pytest_localstack.contrib.botocore.contribute_to_session(session)
    Add BotoCoreTestResourceFactory to LocalstackSession.

pytest_localstack.contrib.botocore.create_credential_resolver()
    Create a credentials resolver for Localstack.

pytest_localstack.contrib.botocore.patch_fixture(scope='function', services=None,
    autouse=False, docker_client=None,
    region_name='us-east-1', kine-
    sis_error_probability=0.0, dy-
    namodb_error_probability=0.0,
    container_log_level=10, lo-
    calstack_verison='latest',
    auto_remove=True,
    pull_image=True,
    container_name=None, **kwargs)
```

Create a pytest fixture that temporarially redirects all botocore sessions and clients to a Localstack container.

This is not a fixture! It is a factory to create them.

The fixtures that are created by this function will run a Localstack container and patch botocore to direct traffic there for the duration of the tests.

Since boto3 uses botocore to send requests, boto3 will also be redirected.

Parameters

- **scope** (*str, optional*) – The pytest scope which this fixture will use. Defaults to "function".
- **services** (*list, dict, optional*) – One of
 - A *list* of AWS service names to start in the Localstack container.
 - A *dict* of service names to the port they should run on.

Defaults to all services. Setting this can reduce container startup time and therefore test time.

- **autouse** (`bool, optional`) – If `True`, automatically use this fixture in applicable tests. Default: `False`
- **docker_client** (`DockerClient, optional`) – Docker client to run the Localstack container with. Defaults to `docker.client.from_env()`.
- **region_name** (`str, optional`) – Region name to assume. Each Localstack container acts like a single AWS region. Defaults to "us-east-1".
- **kinesis_error_probability** (`float, optional`) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into Kinesis API responses.
- **dynamodb_error_probability** (`float, optional`) – Decimal value between 0.0 (default) and 1.0 to randomly inject ProvisionedThroughputExceededException errors into DynamoDB API responses.
- **container_log_level** (`int, optional`) – The logging level to use for Localstack container logs. Defaults to `logging.DEBUG`.
- **localstack_verison** (`str, optional`) – The version of the Localstack image to use. Defaults to "latest".
- **auto_remove** (`bool, optional`) – If `True`, delete the Localstack container when it stops. Default: `True`
- **pull_image** (`bool, optional`) – If `True`, pull the Localstack image before running it. Default: `True`
- **container_name** (`str, optional`) – The name for the Localstack container. Defaults to a randomly generated id.
- ****kwargs** – Additional kwargs will be passed to the `LocalstackSession`.

Returns A pytest fixture.

boto3

pytest-localstack extensions for boto3.

```
class pytest_localstack.contrib.boto3.Boto3TestResourceFactory(localstack_session)
    Create boto3 clients and resources to interact with a LocalstackSession.
```

Parameters `localstack_session` (`LocalstackSession`) – The session that this factory should create test resources for.

client (`service_name`)

Return a patched boto3 Client object that will use localstack.

Arguments are the same as `boto3.client()`.

default_session

Return a default boto3 Localstack Session.

Most applications only need one Session.

resource (`service_name`)

Return a patched boto3 Resource object that will use localstack.

Arguments are the same as `boto3.resource()`.

session(*args, **kwargs)

Return a boto3 Session object that will use localstack.

Arguments are the same as `boto3.session.Session`.

`pytest_localstack.contrib.boto3.contribute_to_session(session)`

Add `Boto3TestResourceFactory` to `LocalstackSession`.

CHAPTER 6

Change Log

6.1 0.1.3 (2018-07-17)

- Fix for botocore >= 1.10.58.

6.2 0.1.2 (2018-06-22)

- Broke out LocalstackSession into RunningSession which doesn't start localstack itself.

6.3 0.1.1 (2018-04-23)

- Fixed bug where patched botocore clients wouldn't populated the *_exceptions* attribute.

6.4 0.1.0 (2018-03-13)

- Initial release

CHAPTER 7

Indices and tables

- genindex
- modindex
- search

Python Module Index

p

`pytest_localstack.contrib`, 15
`pytest_localstack.contrib.boto3`, 17
`pytest_localstack.contrib.botocore`, 15
`pytest_localstack.hooksspecs`, 14
`pytest_localstack.plugin`, 15

Index

B

Boto3TestResourceFactory (class
 in [pytest_localstack.contrib.boto3](#), 17)
BotocoreTestResourceFactory (class
 in [pytest_localstack.contrib.botocore](#), 15)

C

client() ([pytest_localstack.contrib.boto3.Boto3TestResourceFactory](#) method), 15
client() ([pytest_localstack.contrib.botocore.BotocoreTestResourceFactory](#) method), 15
construct_endpoint() ([pytest_localstack.contrib.botocore.LocalstackEndpointResolver](#) method), 16

contribute_to_module() (in module
 [pytest_localstack.contrib.botocore](#), 16)

contribute_to_module() (in module
 [pytest_localstack.hookspecs](#), 14)

contribute_to_session() (in module
 [pytest_localstack.contrib.boto3](#), 18)

contribute_to_session() (in module
 [pytest_localstack.contrib.botocore](#), 16)

contribute_to_session() (in module
 [pytest_localstack.hookspecs](#), 14)

create_client() ([pytest_localstack.contrib.botocore.Session](#) method), 16

create_credential_resolver() (in module
 [pytest_localstack.contrib.botocore](#), 16)

D

default_session ([pytest_localstack.contrib.boto3.Boto3TestResourceFactory](#) attribute), 17
default_session ([pytest_localstack.contrib.botocore.BotocoreTestResourceFactory](#) attribute), 15

DefaultCredentialProvider (class
 in [pytest_localstack.contrib.botocore](#), 15)

G

get_available_endpoints()
 ([pytest_localstack.contrib.botocore.LocalstackEndpointResolver](#))

method), 16
in [get_available_partitions\(\)](#)
 ([pytest_localstack.contrib.botocore.LocalstackEndpointResolver](#) method), 16

L

load() ([pytest_localstack.contrib.botocore.DefaultCredentialProvider](#) method), 15
LocalstackEndpointResolver (class in [pytest_localstack.contrib.botocore](#), 16)

LocalstackSession (class in [pytest_localstack.session](#)), 13

P

patch_botocore() ([pytest_localstack.contrib.botocore.BotocoreTestResourceFactory](#) method), 15
patch_fixture() (in module [pytest_localstack](#)), 11
patch_fixture() (in module
 [pytest_localstack.contrib.botocore](#), 16)
pytest_localstack.contrib (module), 15
pytest_localstack.contrib.boto3 (module), 17
pytest_localstack.contrib.botocore (module), 15
pytest_localstack.hookspecs (module), 14
pytest_localstack.plugin (module), 15
pytest_localstack_hookimpl (in module
 [pytest_localstack.hookspecs](#)), 14

R

register_plugin_module() (in module
 [pytest_localstack.plugin](#)), 15
ResourceFactory ([pytest_localstack.contrib.boto3.Boto3TestResourceFactory](#) method), 17

Session (class in [pytest_localstack.contrib.botocore](#)), 16

session() ([pytest_localstack.contrib.boto3.Boto3TestResourceFactory](#) method), 17
session() ([pytest_localstack.contrib.botocore.BotocoreTestResourceFactory](#) method), 15

session_fixture() (in module [pytest_localstack](#)), 12
Session (class in [pytest_localstack.contrib.botocore](#)), 16
session() ([pytest_localstack.contrib.boto3.Boto3TestResourceFactory](#) method), 17
session() ([pytest_localstack.contrib.botocore.BotocoreTestResourceFactory](#) method), 15

session_started()	(in	module
	pytest_localstack.hookspecs),	14
session_starting()	(in	module
	pytest_localstack.hookspecs),	14
session_stopped()	(in	module
	pytest_localstack.hookspecs),	15
session_stopping()	(in	module
	pytest_localstack.hookspecs),	15

V

valid_regions (pytest_localstack.contrib.botocore.LocalstackEndpointResolver attribute), 16